



Education Software Installer 2015

INSTALLATION GUIDE

FOR MAC OS X OPERATING SYSTEM SOFTWARE

SMART[®]

Trademark notice

SMART Notebook, SMART Ink, SMART Response, smarttech, the SMART logo and all SMART taglines are trademarks or registered trademarks of SMART Technologies ULC in the U.S. and/or other countries. Mac, OS X, Safari and Finder are trademarks of Apple Inc., registered in the U.S. and other countries. All other third-party product and company names may be trademarks of their respective owners.

Copyright notice

© 2015 SMART Technologies ULC. All rights reserved. No part of this publication may be reproduced, transmitted, transcribed, stored in a retrieval system or translated into any language in any form by any means without the prior written consent of SMART Technologies ULC. Information in this manual is subject to change without notice and does not represent a commitment on the part of SMART.

This product and/or use thereof covered by one or more of the following U.S. patents.

www.smarttech.com/patents

12/2015

Getting started

This guide explains how to install the following software using the Education Software Installer:

- SMART Notebook® 15.2 collaborative learning software
- SMART Product Drivers 12.4
- SMART Ink™ 3.2
- SMART Response® 2015 assessment software
- Handwriting recognition
- SMART Common Files

This guide is intended for teachers, IT administrators and others who are responsible for installing software on teachers' computers.

To use this guide, you must have access to the installation DVD or the Internet.

Computer requirements



NOTE

Operating systems and other third-party software released after this SMART software might not be supported.

Before you install the software, ensure your teachers' computers meet the minimum requirements:

- Intel® Core™ 2 Duo processor or better
- 2 GB of RAM

- Free hard disk space:

Software	Space required
SMART Notebook software	178 MB
Gallery Essentials	544 MB
Lesson Activity Toolkit	111 MB
SMART Product Drivers	188 MB
SMART Ink	24 MB
SMART Response software	211 MB
Handwriting recognition	63 MB (24-60 MB for additional languages)
SMART System Menu	3 MB
SMART Common Files	938 MB
Recommended total free hard disk space	2.3 GB

- OS X 10.9, 10.10 (Yosemite), 10.11 operating system software
- Adobe® Flash® Player 19 for SMART Notebook software
- Safari application program 4.0.2 or later
- Internet access to download SMART software



IMPORTANT

Some features require access to specific websites. You might need to whitelist those websites if you restrict outbound Internet access. For further information, see [SMART Notebook and SMART Response VE add-ons behave unexpectedly behind a firewall or proxy](#).

Deploying the software

If you're an IT administrator and you want to deploy the software to multiple computers, see the *Education Software Installer 2015 system administrator's guide* (smarttech.com/kb/170901).

Installing the software

Starting the installer

You can start the installer by inserting the DVD into the computer or by downloading the installer from the SMART website.

To start the installer from the DVD

1. Insert the DVD into the computer.

The *Education Software Installer* dialog box appears.



NOTE

If the dialog box doesn't appear, use Finder to browse to and open **[DVD]** `/esi2015august.dmg`.

2. Click **Install**.

The installer appears.

To download and start the installer from the website

1. Go to smarttech.com/software, click the **Choose a version** button for the software you want to install, and then select the version of the software you want to install.
2. Click **Download**.
3. Read the important notice that appears, because terms have changed, and then click the **Continue with Download** link.
4. Save the file to a temporary location.
5. Double-click the file.

The installer appears.

To install the software using the installer

1. Start the installer as described in the previous procedures.
2. Click **Continue**.
3. Review the terms in the software license agreement, and if you accept the terms, click **Agree**.
4. Select the check box if you want to join the Customer Experience Program, and then click **Continue**.
5. Select the disk on which you want to install the software, and then click **Continue**.

6. Select the software you want to install.



NOTE

SMART Notebook and **SMART Product Drivers** are selected by default. Handwriting recognition (English) is selected by default. You can select other languages if you want handwriting recognition in other languages.

7. If you selected **SMART Notebook** in step 6, click its disclosure triangle, and then select the Gallery collections you want to install.
8. If you selected **SMART Response** in step 6, click its disclosure triangle, and then select **Start Desktop Menu at log in** to start SMART Response software when you first log on to your computer.
9. If you selected **SMART Product Drivers** in step 6, click its disclosure triangle, and then select **Start SMART System Menu at log into** to start the SMART System Menu when you first log on to your computer.
10. If you selected **SMART Ink** in step 6, click its disclosure triangle, and then select **Make SMART Ink Document Viewer the default PDF viewer** to set the SMART Ink Document Viewer as the default program used to open PDF files.
11. Click **Continue**.
12. Click **Install**.

A dialog box appears, prompting you for your name and password.
13. Type your name and password, and then click **OK**.

The installer installs the software you selected in step 6.

Removing the software

You can remove SMART software using SMART Uninstaller.

To remove SMART software

1. In Finder, browse to and double-click **Applications/SMART Technologies/SMART Uninstaller**.
2. Select the software you want to remove.



NOTES

- Some SMART software is dependent on other SMART software. For example, if you select **SMART Notebook**, SMART Uninstaller removes SMART Response software automatically because SMART Response software is dependent on SMART Notebook software.
- SMART Uninstaller automatically removes any supporting software that is no longer used. If you choose to remove all SMART software, SMART Uninstaller automatically removes all supporting software, including itself.



TIPS

- To select more than one application, hold down SHIFT or COMMAND while selecting the applications.
- To select all software applications, click **Select All**.

3. Click **Remove**, and then click **OK**.
4. If prompted, enter a user name and password with administrator privileges, and then click **OK**.
SMART Uninstaller removes the selected software.
5. Close SMART Uninstaller when done.

SMART TECHNOLOGIES

smarttech.com/support

smarttech.com/contactsupport

smarttech.com/kb/170899